2018/03/26 05:33 1/2 Launchpad/Default Site

# Launchpad/Default Site

Starting Version 5.8, the concepts of a Launchpad and a Default Site were introduced to facilitate user access when the same business has multiple sites, say, an ERP site, a Web Store and an Employee Portal.

### **Default Site**

The default site can be expressly defined in

```
System Administration->Settings->Defaults
```

If you do not define a default site, the system automatically determines default site in the following manner:

- If there is only one active site in the business, it automatically assumed to be the default site, or lese
- If you have an active site named Home in the business, or else
- If you have an active site named ERP in the business, or else
- Any active site randomly assigned.

## **Direct Access through URL**

To access a site directly from your URL, say, mydomain.com, use

- http://mydomain.com to access the directory.
- <a href="http://myshortname.mydomain.com">http://myshortname.mydomain.com</a> to access the default site of the business whose short name is myshortname.
- http://mysitename.myshortname.mydomain.com to access the site mysitename.

#### Notes:

(1) For the global directory to work correctly, make sure your system has business id 1 which implements the global directory. Run the following SQL commands from initiate to update the site.

```
update zbusiness set zorg='Directory of Sites' where zid=1;
update pxskins set xtemplate='Global.html', xcss='Global.css' where zid=1;
update pxsites set xpathsite='' where zid=1;
```

(2) Copy the **index.html** from the repository and overwrite the existing one on both **da** and **ROOT** contexts.

## The Launchpad


Last update: 2016/12/12 06:48

The Launchpad is the default Home site for a business which can be used by the internal users to launch various sites in the business. When you launch a site from the Launchpad, you always return to Launchpad. Outside users may be given only the URL directly going to the sites of their interest.

To install Launchpad for a business, after logging in to the ERP site, delete the portal as well as the skin with the name **Home**, if any. Thereafter, change the page parameter to **page=catest** to start the test page. Once in **catest**, Run the command

#### call caaddhome

Now, if you click on the company name/logo in the Directory or access using <a href="http://myshortname.mydomain.com">http://myshortname.mydomain.com</a> you will be taken to the Launchpad of the business.



From:

http://wiki.dreamapps.com/wiki/ - DreamApps Wiki

Permanent link:

http://wiki.dreamapps.com/wiki/doku.php?id=usage:launchpad

Last update: 2016/12/12 06:48

